

KEEPING LEVEL
 Expert

ORIGIN
 Asia

NEST TEMPERATURE
 24–28°C

NEST HUMIDITY
 60–80%

WORKERS BEFORE
NEST
 10+

At a glance

Origin	 South and Southeast Asia — India, Nepal, Bangladesh, Thailand, Laos, Vietnam, southern China, Malaysia, Borneo and Indonesia
Keeping level	Expert — a live-food hunter that needs steady warmth and humidity
Queen	18–20mm, dark brown to black, with long sickle-shaped mandibles
Workers	16–18mm, one size, slender with huge eyes
Colony form	Single queen; if she dies, a mated worker (gamergate) can take over egg-laying
Founding	Semi-claustral — the queen hunts for her first brood
Mature colony	Small — usually tens to a few hundred workers
Nest temperature	24–28°C
Nest humidity	60–80%
Workers before moving into a nest	10+
Winter	No hibernation — keep warm all year

About this species

The ant on our logo! Harpegnathos venator is a primitive ponerine hunter with enormous eyes and long sickle-shaped mandibles. Workers stalk and leap onto prey — a show unlike any other ant. Colonies are small and slow-growing, so every worker counts. A secure lid and a fresh PTFE band are essential: these ants can jump.

 **Sting:** workers have a functional sting. Painful but not dangerous for most people — adults only.

When your ants arrive

-  **MOST IMPORTANT:** leave the parcel completely unopened, exactly as it arrived, at room temperature for **5 hours**. The ants must adjust to your home's temperature gradually — abrupt temperature changes make ants seriously unwell.
- After the 5 hours, check the queen is safe and sound, then leave the colony in its original packaging (test tube still in its tin foil and wrapping) in a quiet spot — in daylight, never direct sunlight — away from vibration and daily household activity.
-  Give the colony **4 to 5 days** of complete rest. The ants were fed before dispatch and need nothing from you during this time. Assemble and water the nest while you wait.
- Still workers or a motionless queen after delivery are almost always delivery stress. Check the antennae: moving antennae means she is fine. Almost all recover within 4 to 5 days (a little longer for bigger queens).
- Do not remove the black divider inside the test tube (between the two cotton stoppers) — it keeps the ants safe in transit. It has a hole, and the queen and all workers pass through it without any issue.
-  Start with a colony, never a lone queen or a single worker: choose at least 10 workers with eggs, larvae or pupae laid inside that colony (not added from elsewhere) — that is your proof of a fertile egg-layer. The egg-layer often looks almost identical to the workers, so the brood is the only reliable sign for most keepers. The more workers, the better your chance of success.

Moving into the ant farm

- Keep the colony in its test tube until it has at least 10 workers. Moved earlier, the workers often abandon the queen in the larger space, which can lead to colony failure.
- Connect the test tube to the nest with the delivery tin foil still on and leave it for 14 days. Then slide the foil back about 1mm every day until the tube is fully exposed to daylight.
- If the ants have not moved in 2 days after the tube is fully exposed, wrap the foil back on, wait another fortnight and repeat the whole process — patience is the key. Moving in happens on the ants' own time: anywhere from a couple of days to 6 months.
- The red filter and black cover stay on the nest at all times — it is pitch dark inside. The black cover can come off once a day for 2 to 3 minutes (ideally at night); the red filter once a week for 2 to 3 minutes.
-  Place the ant farm in normal daylight, never direct sunlight (the sun can overheat a nest within minutes). Avoid windows, radiators and heaters, vibrating surfaces, speakers and TVs, strong smells such as the kitchen, and busy walkways. Keep a steady room temperature.



Feeding

-  **Live prey is the heart of this species' diet** — it is a true hunter and will not thrive on jelly alone. Offer small live crickets, flightless fruit flies or small cockroach nymphs such as our Red Runner Roaches — 2 to 3 times a week, in the outworld only, sized so a single worker can overpower it.
-  Buy live food only from a clean, trusted breeder and check it for mites before it goes in — mites can destroy a colony, starting with the queen. Larger prey the ants accept pre-killed (mealworms, crickets, locusts) should be scalded first: hold it with tweezers in just-boiled water (no longer bubbling) for 10 to 15 seconds, chop it in half and serve on a small tin foil tray.
-  NextSwarm Cricket Mash is a useful protein top-up between hunts. Sugars are only a small part of their diet: a tiny drop of organic honey or Ant Nectar once a week is plenty, and some colonies ignore it, which is normal.
-  Remove leftovers and uneaten prey after 2 days to prevent mould. A springtail clean-up crew in the outworld helps keep things tidy.

Watering the nest

-  Use **distilled or purified water only** — never tap, rainwater or bottled mineral water, even boiled. They carry minerals and microbes that turn a nest green with mould. A litre of distilled water costs a few pounds and lasts over a year.
- Water the nest with the pipette provided: pour slowly, a few drops at a time, through the watering hole, and stop as soon as 1 or 2 drops appear inside the nest — that is how you know it is done correctly. More than that is too much.
- Once a week is usually right — slightly more in summer, less in winter. Never water the outworld.

Temperature and winter

-  No hibernation. Harpegnathos venator comes from a warm climate and must stay at 24–28°C all year round — in a UK home this means gentle heating in the cooler months.
- Use the Advanced Heating System Small 4W warming no more than a quarter of the nest, on the side opposite the water inlet, so the ants can choose their temperature. For a colony still in its test tube, use the Heating Mat with Thermostat Small 4W and heat only about 25mm of the tube, at the end opposite the water — never lay the whole tube on the mat.
- Never let the colony get cold, and never expose it to abrupt temperature changes.

★ Golden rules | Never break these

-  Never put ants in a fridge, and never expose them to abrupt temperature changes. Cold does not kill a colony instantly — the ants get sick and die over the following days — and prolonged cold near freezing damages the sperm a queen stores from her nuptial flight, so she may never lay fertile eggs again.
-  Never use gel ant farms, Ytong or concrete nests, or DIY nests.
-  Never use tap, rain or mineral water, even boiled.
-  Never move a colony into a nest too early, and never tip or shake ants out of their tube.
-  Never disturb the colony with tapping or handling — vibration stresses the queen and she can stop laying or eat her eggs.
-  Never keep the farm in the dark: ants need daylight for their circadian rhythm. Daylight yes — direct sunlight never.
-  Choose a nest with a pre-installed humidity and temperature meter (our A5 M PLA or A4-2 Smart Meter) — humidity is impossible to check any other way, and it matters most for these species.
-  Never handle these ants or let children handle the setup — always use long tweezers and keep the lid closed and the PTFE band fresh.



Recommended for this species

Harpegnathos venator colony

A5 M PLA Ant Farm with Meter

PTFE Escape Barrier

Advanced Heating System 4W

Test Tube Heating Mat 4W

Red Runner Roaches

Cricket Mash

Springtails Clean-up Crew



These care notes cover the essentials only. Please read the full [ant farm setup guide](#) and [our Harpegnathos venator article](#) from A to Z — we recommend printing both for a successful ant-keeping experience. Questions? Message us through our [contact form](#) — we are always happy to help. ❤️

Written and reviewed by the Best Ants UK team, keeping ants since 1997.